### **NAME**

DPMSInfo – returns information about the current DPMS state

#### **SYNOPSIS**

#### **ARGUMENTS**

```
    display Specifies the connection to the X server
    power_level Specifies the current power level
    state Specifies the current DPMS state
```

# **DESCRIPTION**

The *DPMSInfo* function returns information about the current Display Power Management Signaling (DPMS) state. The *state* return parameter indicates whether or not DPMS is enabled (TRUE) or disabled (FALSE). The *power\_level* return parameter indicates the current power level (one of DPMSModeOn, DPMSModeStandby, DPMSModeSuspend, or DPMSModeOff.)

# **RETURN VALUES**

TRUE The *DPMSInfo* function returns TRUE, if values are returned.

FALSE The *DPMSInfo* function returns FALSE, if no values are returned.

### **SEE ALSO**

**DPMSEnable**(3)