

**NAME**

sane-sceptre – SANE backend for SCEPTRE scanners

**DESCRIPTION**

The **sane-sceptre** library implements a SANE (Scanner Access Now Easy) backend that provides access to Sceptre flatbed scanners. This backend should be considered **beta-quality** software! Please report any strange behavior to the maintainer of the backend or to the SANE mailing list.

At present, only one scanner is known to work with this backend:

| Model                   | Connection Type |
|-------------------------|-----------------|
| -----                   | -----           |
| Sceptre VividScan S1200 | SCSI            |

The make of this scanner is KINPO, so other scanners from that manufacturer may also work (eg. the S600).

**OPTIONS**

The options the backend supports can either be selected through command line options to programs like **scanimage**(1) or through GUI elements in **xscanimage**(1) or **xsane**(1).

Valid command line options and their syntax can be listed by using

```
scanimage --help -d sceptre
```

**Scan Mode****--mode Linear|Halftone|Gray|Color**

Selects the basic mode of operation of the scanner. The *Linear* and *Halftone* mode are black and white only (1 bit). *Gray* will produce 256 levels of gray (8 bits). *Color* will produce a 24 bits color image. The scanner supports 30 bits internally but it only exports 24.

**--resolution 50..1200**

Selects the resolution for a scan. The scanner can do several resolutions between 50 and 1200.

**--halftone-pattern 1|2|3|4**

Selects the pattern mode that is used in *Halftone* mode.

**--gamma-correction Default|User Defined|High Density Printing|Low density printing|High contrast printing**

controls the scanner internal gamma correction.

**--custom-gamma**

Allows the user to specify a gamma table (see the next 3 parameters). *Color* mode only.

**--red-gamma-table**

Can be used to download a user defined gamma table for the red channel. The table must be 256 bytes long. *Color* mode only.

**--green-gamma-table**

Can be used to download a user defined gamma table for the green channel. The table must be 256 bytes long. *Color* mode only.

**--blue-gamma-table**

Can be used to download a user defined gamma table for the blue channel. The table must be 256 bytes long. *Color* mode only.

**--threshold 0..255**

Sets the threshold for black and white pixels in *Lineart* mode. Possible values are from 0 (darker) to 255 (lighter).

**--preview**

Requests a preview scan. The resolution used for that scan is 30 dpi and the scan area is the maximum allowed. The scan mode is user selected. The default is "no".

**The geometry options****-l -t -x -y**

control the scan area: **-l** sets the top left x coordinate, **-t** the top left y coordinate, **-x** selects the width and **-y** the height of the scan area. All parameters are specified in millimeters by default.

**CONFIGURATION FILE**

The configuration file `/etc/sane.d/sceptre.conf` supports only one item: the device name to use (eg `/dev/scanner`).

**FILES**

`/usr/lib/x86_64-linux-gnu/sane/libsane-sceptre.a`

The static library implementing this backend.

`/usr/lib/x86_64-linux-gnu/sane/libsane-sceptre.so`

The shared library implementing this backend (present on systems that support dynamic loading).

**ENVIRONMENT****SANE\_DEBUG\_SCEPTRE**

If the library was compiled with debug support enabled, this environment variable controls the debug level for this backend. E.g., a value of 128 requests all debug output to be printed. Smaller levels reduce verbosity.

**LIMITATIONS****Resolutions**

The windows TWAIN driver can be set to any resolution between 50 to 1200 (excluding software interpolation). This backend cannot. Only a handful of resolution are available, although they should be numerous enough.

**BUGS**

None known.

**SEE ALSO**

**sane-scsi(5), scanimage(1), xscanimage(1), xsane(1), sane(7)**

**AUTHOR**

The package is actively maintained by Frank Zago.

*<http://www.zago.net/sane/#sceptre>*